

# Connecting to the U, W, and P Drives for Mac OS X Snow Leopard

AgIT Systems


Procedure No. S1.3.58

## Procedure Statement

There is a different method to connect to the U, W, and P drives. This procedure outlines the method for each.

### Connecting to the U Drive

1. In **Finder**, select **Go**.
2. Choose **Connect to Server**.
3. The **Connect to Server** box will appear. In the **Server Address:** field, type **smb://114x-files/udrive**
4. Click on the **Connect** button.



### *To Create a Desktop Shortcut:*

1. While looking at the contents of U, press the apple key and the up arrow to move up a directory
2. Select the U drive folder while holding down the apple key and alt key, and drag the shortcut onto your desktop

### Connecting to the W Drive

1. In **Finder**, select **Go**.
2. Choose **Connect to Server**.
3. The **Connect to Server** box will appear. In the **Server Address:** field, type **smb://1144agadnt/pub**
4. Click on the **Connect** button.

# Connecting to the U, W, and P Drives for Mac OS X Snow Leopard

AgIT Systems

Procedure No. S1.3.58

In the Server Address: field, type **smb://1144agadnt/pub**



Click the **Connect** button.


*To Create a Desktop Shortcut:*

1. While looking at the contents of Pub, press the apple key and the up arrow to move up a directory
2. Select the Pub folder while holding down the apple key and alt key, and drag the shortcut onto your desktop

Connecting to the P Drive


1. In **Finder**, select **Go**.
2. Choose **Connect to Server**.
3. The **Connect to Server** box will appear. In the **Server Address:** field, type **smb://1157countyname**
4. Click on the **Connect** button.

In the Server Address: field, type **smb://1157countyname**



Click the **Connect** button.


5. A box will appear reading: *Select to volumes you want to mount on "1157countyname"* Select **Home** for user and shared storage.
6. Click the **OK** button.



## Connecting to the U, W, and P Drives for Mac OS X Snow Leopard

AgIT Systems

*Procedure No. S1.3.58*



You have now connected to the P drive.

### To Create a Desktop Shortcut

1. While looking at the contents of P, press the apple key and the up arrow to move up a directory
2. Select the folder you would like to have a shortcut to (in most cases, it should be **H**ome) while holding down the apple key and alt key, and drag the shortcut onto your desktop